

INCORRECT WAY TO CONNECT IMIRA

DO NOT CONNECT YOUR COMPUTER DIRECTLY
TO IMIRA FOR THE INSTALLATION PROCESS.



CORRECT WAY TO CONNECT IMIRA

MAKE SURE TO CONNECT BOTH YOUR
COMPUTER AND iMIRA TO THE SAME
WI-FI NETWORK.



1.1 INSTALL SERVER SOFTWARE

Installation Package:

- iMiraServer
- i-Maker2

To start off with the server software installation, double click on "iMiraServer".

Note:

- Please make sure that your computer is connected to a Wi-Fi Network.
- iMira2 servers only work with Windows.



GRUPO
HU
华海集团

Step 1:

- Choose your language, click "Ok".




Step 2:

- System Description, click "Next".



Step 3:

- License agreement.
You must click on "I Agree".



Step 4:


- Make sure that all boxes are selected just like on this photo, then click "Next".



Step 5:

- Select where in your computer you want the server to be installed by clicking on "Browse" and then "Install".


The whole installation process might take from 2 to 3 minutes



Step 6:


- If your computer's firewall is on, you will see this message on your screen. This only appears to protect your computer from unwanted content.

Please click on "Allow Access".




Step 7:

- Click "Finish" to be done with the installation.



Step 8:

- You should see this message "Service Started" if the installation was successfully installed.



2.1 INSTALL CONTROL SOFTWARE

Installation Package:

- iMiraServer
- i-Maker2

To start off with the control software installation, double click on "i-Maker2".


Note:

- Please make sure that your computer is connected to a Wi-Fi Network.
- iMira2 servers only work with Windows.



Step 1:

- Choose your language, click "OK".



Step 2:


- System Description, click "Next".



Step 6:


- Setting Control Software
i-Maker3 login box will appear after you click on the program installed previously.

Type "admin" on account and "admin" on password. Then click on login.




Step 7:

- Click on "Program Produce" to start managing the content for iMira. 华海集团




Step 8:

- Click on "Systems Settings" at the bottom left of the screen. Make sure you copy your "Server IP" because you will need it to connect your iMira to your network.




Step 9:

- To start with the content management please click on "Program" located on the left of the window. Choose the option that better suits your project and then click "Ok".




Step 10:

- Select block and double click on it.



Step 11:


- On this new window you will be able to upload your content to display on your iMira.
Click on "Media Upload" to search and upload your content such as: video, picture, text, etc. Once it is uploaded click "OK" to continue.



Step 12:

- Type a name to save to project in the Content Management platform.



Click on "OK".



Step 13:


- Click "Release" and make sure all boxes shown on the second picture are selected.

Then click "Next".




Step 13:

- Release Program Wizard
On this window select the options according to your needs. Then, click "Finish".



Step 14:

- Click on "Screen Management" on the left side of the window to check the status terminal.
If everything was successfully created, you will see a green bar on the "Down Percentage" section.



IMPORTANT DETAILS

- **Setting Server IP**

Make sure to have a regular mouse connected to the USB port of your iMira.

Right click anywhere on the screen to access the settings menu.

Click on "Server IP" and enter the same Server IP you copied in Step 8 of this manual.

Click "Confirm" and make sure that the "Status" has the message "Connection Succeed".

Right click anywhere on the screen again to go back to your home page.

